

Obtaining SDO/AIA and SDO/HMI data

(adapted in part from an Introduction to SDO by Daniel Brown, Stephane Regnier, Mike Marsh, and Danielle Bewsher UNIVERSITY OF CENTRAL LANCASHIRE)

1 Introduction

The Solar Dynamics Observatory (SDO) is a NASA mission that was launched in February 2010 to study the dynamics of the solar atmosphere and interior. It comprises three instruments, the Atmospheric Imaging Assembly (AIA), the Helioseismic and Magnetic Imager (HMI), and Extreme Ultraviolet Variability Experiment (EVE). AIA and HMI are both imaging instruments with both high spacial and temporal resolution in a range of spectral bands/data products, producing ~ 1.5 TB of data per day.

This large data set means that obtaining and analyzing data becomes a tricky process. It will often be the case that all the data required for an analysis can not be held in a computers memory at once. Researchers using SDO data will have to be clever about how data acquisition and analysis is performed.

1.1 Browsing for SDO data

Several sites offer visual browsing of the latest solar data, with options to review previous days in the archive. These sites are often useful for a quick look, but not so useful for obtaining data.

Some useful sites are

- **The Sun Today** offered by Lockheed (<http://sdownwww.lmsal.com/suntoday.html>) shows up-to-date images of the Sun in all AIA wavelengths and provides information from an events catalog.
- **Helioviewer** (<http://www.helioviewer.org>) is a useful tool to visualise large amounts of data. This is an open source program. A database of the last 14 years of SOHO data as JPEG images are available using the online viewer or by installing the JHelioviewer on your computer (this requires the latest version of Java to be installed on your computer). This tool will be soon evolve to provide SDO/AIA images as JPEG 2000. There are options to produce movies, zooming and saving the results.

2.2 Data Archives

There are several ways to obtain observation from AIA and HMI.

The following are essentially web portals, where a web form is filled in with the required date/time and wavelength parameters, and a data request is made for subsequent download.

- From the HMI-AIA Joint Science Operations Center (JSOC - <http://jsoc.stanford.edu/>) based at Stanford University;

- From the AIA cutout service at Lockheed (http://lmsal.com/get_aia_data/) which allows smaller cutouts from the data to be extracted and downloaded;
- From the Virtual Solar Observatory (VSO - <http://sdac.virtualsolar.org/cgi/search>).

However, the VSO also has tools in the SolarSoftWare tree for obtaining data through SSWIDL. We will utilize this method in this tutorial.

2.3 Obtaining data via the VSO in SSW

SSW provides a set of commands for interacting with the Virtual Solar Observatory directly from within the SSWIDL environment. Two of these are of particular interest for downloading SDO data (and any other data in the VSO). These are:

- `vso search` - which searches for data matching supplied time/date/instrument/wavelength/etc specifications;
- `vso get` - attempts to download data corresponding to the meta-data from a previous VSO search.

2.3.1 Searching for data - `vso search`

A typical VSO search might be carried out as follows

```
IDL> md=vso_search('2010/08/01 10:00:00', '2010/08/01 10:05:00', $
instr='aia')
```

which will search for all AIA data between 10:00 and 10:05 on 1st August 2010. This call will display search results similar to

```
Records Returned : JSOC : 187/187
Records Returned : JSOC : 0/0
```

which means that 187 observations were found in one catalog and none were found in a second catalog. In this case, the two catalogs were based at the JSOC, and refer to the AIA level 1 (4096 × 4096) catalog, and the AIA synoptic (1024 × 1024) catalog. Other catalogs may come on line in the future as other SDO providers feed in to the VSO.

The `vso search` routine has downloaded meta-data associated with the found observations and stored them as a structure array in the variable `md`. The meta-data can be viewed with

```
IDL> help, md, /str
```

which displays the meta-data of the first record, something like the following:

```
** Structure VSORECORD, 13 tags, length=256, data length=252:
```

```
TIME STRUCT -> VSOTIME Array[1]
EXTENT STRUCT -> VSOEXTENT Array[1]
WAVESTRUCT -> VSOWAVE Array[1]
DETECTOR STRING ""
INSTRUMENT STRING 'AIA'
SOURCE STRING 'SDO'
PROVIDER STRING 'JSOC'
INFO STRING 'AIA level 1, 4096x4096'
PHYSOBS STRING 'intensity'
FILEID STRING 'aia_lev1:171:1059732035'
SIZE FLOAT 66200.0
URL STRING ""
GETINFO STRING ""
```

As md is an array, meta-data for any specific observation can be viewed by specifying its number, i.e.,

```
IDL> help, md(10), /str
```

The meta-data structure also contains some sub-structures which can be viewed by

```
IDL> help, md.wave, /str
```

which displays something similar to

```
** Structure VSOWAVE, 4 tags, length=40, data length=40: MIN      FLOAT      171.000
MAX FLOAT      171.000
TYPE STRING    'NARROW'
UNIT STRING    'Angstrom'
```

So, it is clear that this particular observation is made using the 171 A° filter. Looking at the next observation

```
IDL> help, md(1).wave, /str
```

```
** Structure VSOWAVE, 4 tags, length=40, data length=40: MIN      FLOAT      304.000
MAX FLOAT      304.000
TYPE STRING    'NARROW'
UNIT STRING    'Angstrom'
```

it is clear that this observation is made using the 304 A° filter. The wavebands for the first few observations can be viewed with

```
IDL> print, md(0:14).wave.min
```

171.000	304.000	94.0000	4500.00	171.000
304.000	1600.00	94.0000	171.000	304.000
1700.00	94.0000	171.000	304.000	1600.00

showing that observation in several different pass-bands have been picked up.

The VSO search can be refined further, for example, the search can be restricted to a fixed wavelength using the wave keyword in vso search, i.e.,

```
IDL> md304 = vso_search('2010/08/01 10:00:00', '2010/08/01 10:05:00', $  
instr='aia', wave='304') Records Returned : JSOC : 25/25  
Records Returned : JSOC : 0/0
```

which finds 25 observations in the 304 Å pass-band in the desired time range.

The sample keyword attempts to find a subset of observations that are evenly spread throughout a time-range. For example

```
IDL> md304 = vso_search('2010/08/01 10:00:00', '2010/08/01 22:00:00', $  
instr='aia', wave='304', sample=600)  
will try to find a subset of 304 Å observations in the 12 hour interval which are 600 seconds (10  
minutes) apart. Sometimes, the wave keyword is not enough to specify the required data product. For  
example, HMI data will  
all have the same wavelength range, but will offer different data products (e.g., magnetograms,  
dopplergrams, etc). In this situation the physobs keyword can be used. For example
```

```
IDL> mdhmi = vso_search('2010/08/01 10:00:00', '2010/08/01 10:05:00', $  
instr='hmi', physobs='LOS_magnetic_field')
```

which will find the line-of-sight magnetograms in the specified time range. Other useful values of physobs include physobs='intensity' and physobs='LOS velocity'.

There are a whole range of other keywords that can be used to refine a search. These have not been listed in detail here as they are not necessarily useful for SDO data at the moment (although when more repositories - such as UCLan - feed in to the VSO, then the provider keyword may become useful). More details can be found with an xdoc search of the command.

2.3.2 Downloading data - vso get

Note: during the practical session, please avoid trying to download large amounts of data - there is neither the time or bandwidth to meaningfully do this. Restrict yourself to downloading only a couple of files to try it out, but then use the data provided on the memory sticks.

Once a search has identified suitable data, it needs to be downloaded to the local system. This is done using the

vso get command. In its simplest form, this can be done as follows

```
IDL> md=vso_search('2010/08/01 10:00:00', '2010/08/01 10:00:30', $  
instr='aia') Records Returned : JSOC : 10/10  
Records Returned : JSOC : 0/0  
IDL> status=vso_get(md)
```

This will download the requested files and place them in the current working directory (it may take a while depending on how many files have been requested).

It may more usefully be called with the out_dir keyword which specifies a target directory to copy the files in to, e.g.,

```
IDL> status=vso_get(md, out_dir='/archive/sdo/aia/mydata/')
```

The variable status is a structure array that contains some download information for each file. e.g.,

```
IDL> help,status,/str
```

```
** Structure GETDATARECORD, 5 tags, length=72, data length=68: PROVIDER   STRING  
   'JSOC'  
FILEID   STRING   'aia_lev1:1600:1059732053'  
URL   STRING   'http://vso.tuc.noao.edu/cgi-bin/drms_test/  
drms_export.cgi?series=aia_lev1;re'... INFO   STRING   ''  
SIZE   FLOAT   0.00000
```

The fits files are now in the target directory ready for analysis.

The files that have been downloaded are uncompressed fits files and may have sizes around 65 MB. It is possible to download RICE compressed fits files instead with the keyword /rice, i.e.,

```
IDL> status=vso_get(md, out_dir='/archive/sdo/aia/mydata/', /rice)
```

These files are typically around 5.3 MB, and may improve download times, particularly where there is restricted bandwidth. SSW will automatically uncompress these files when they are read into SSWIDL.

Note 2, when downloading large amounts of data, give some thought to how much space the files will take up (will it fit on the network), how much bandwidth it will need to download (will it clog up everyone else's internet traffic), how long it will take to download (will it still be downloading in a weeks time), and so on.

2.3.3 Further sorting of data

It is possible to apply further sorting to your search in SSWIDL before requesting files. For example

```
IDL> md=vso_search('2010/08/01 10:00:00', '2010/08/01 10:05:00', $  
instr='aia') Records Returned : JSOC : 187/187  
Records Returned : JSOC : 0/0  
IDL> status=vso_get(md(0:4), out_dir='/archive/sdo/aia/mydata/')
```

would retrieve only the first five files found.

```
IDL> md=vso_search('2010/08/01 10:00:00', '2010/08/01 10:05:00', $
```

```
instr='aia') Records Returned : JSOC : 187/187
Records Returned : JSOC : 0/0
IDL> status=vso_get(md([4,15,25]), out_dir='/archive/sdo/aia/mydata/')

```

would retrieve the 5th, 16th and 26th files in the list (remember, IDL starts counting at 0).

```
IDL> md=vso_search('2010/08/01 10:00:00', '2010/08/01 10:05:00', $
instr='aia') Records Returned : JSOC : 187/187
Records Returned : JSOC : 0/0
IDL> ii = indgen(38)*5
IDL> status=vso_get(md(ii), out_dir='/archive/sdo/aia/mydata/')

```

would retrieve every 5th file found.

```
IDL> md=vso_search('2010/08/01 10:00:00', '2010/08/01 10:05:00', $
instr='aia') Records Returned : JSOC : 187/187
Records Returned : JSOC : 0/0
IDL> ii = where(md.wave.min eq '171')
IDL> status=vso_get(md(ii), out_dir='/archive/sdo/aia/mydata/')

```

would identify all of the 171 Å

data from the meta-data and retrieve only those files (though in practice, you might check to see if any 171 Å files had been found first).

Any reasonable IDL array indexing and searching should help refine the search further prior to downloading the data.

Exercise

Select a recent date and download full disk AIA193 Å, full resolution images (do not use /rice) over an hour at a 10 minute cadence. There should be a total of 6 images. Save them in an appropriately named directory.

3 Reading SDO data into SSWIDL

3.1 Using read sdo

Now that some SDO data has been obtained, it needs to be read into SSWIDL. This can be done using the read sdo command. For example

Input the name of the file directly.

```
IDL> read_sdo, 'aia file.fits' index, data
```

Reads in the data from the supplied file aia file.fits, and stores the fits header in the structure index and the SDO image in the array data. Querying the variables should return something like the following

```
IDL> help,index,data
INDEX      STRUCT    = -> MS_020517472001 Array[1]
DATA LONG = Array[4096, 4096]
The size of the SDO image (4096 × 4096) can easily be seen.
```

Multiple files can be read in using find_file or find_files.

```
IDL> files=find_file('/archive/sdo/aia/mydata/'*.fits') ;
Or
IDL> files= find_files('*.fits',' /archive/sdo/aia/mydata/') ; note this time we use find_file(s) when
the directory is listed in this manner
```

```
IDL> read_sdo, files, aindex, adata
```

Querying the output variables should provide information similar to the following:

```
IDL> help,aindex,adata
AINDEX     STRUCT    = -> MS_020517472001 Array[10]
ADATA      LONG = Array[4096, 4096, 10]
In this case, 10 files have been read in, and the size of the structure array, aindex, and the third
dimension of
adata reflect this.
```

Warning: think carefully before reading in large numbers of files at once. If each file is ~ 65 MB, then it doesn't take too many files to fill up the available computer memory. For example, 15 images will require ~ 1 GB of free memory. Exceeding available memory will cause the computer to start swapping leading to a painful decrease in speed.

You may (initially) only want to look at the fits headers of a file/files. This can be done by supplying the /nodata flag to the read sdo command, e.g.,

```
IDL> read_sdo, afiles, aindex, adata, /nodata
IDL> help, aindex, adata
AINDEX     STRUCT    = -> MS_020517472001 Array[10] ADATA      UNDEFINED =
<Undefined>
```

The adata variable is left completely empty allowing the fits headers to be queried (perhaps with further search refinements made) before reading in the data.

It is often the case that only a small part of an SDO image is of interest, and the read sdo routine allows only a sub-field of the data to be read in to SSWIDL. This allows a region to be identified by other means (e.g., by examining only a single image in the sequence), and that selected portion of the image in a larger number of files to be read in at once.

Extracting a Sub-Field Using Read_SDO

To extract a sub-field, four additional inputs are required

```
read_sdo, afiles, aindex, adata, llx, lly, nx, ny
```

where (llx, lly) are the pixel positions of the lower-left corner of the required cutout and (nx, ny) is the size of the sub-field. So

```
IDL> read_sdo, afiles, aindex, adata, 3100, 2300, 800, 800
```

will cut out an 800×800 pixel region from each image with a lower left hand corner located at pixel position (3100, 2300) in the full image. Querying the two variables confirms this, i.e.,

```
IDL> help, aindex, adata
AINDEX      STRUCT      = -> MS_020517472001 Array[10] ADATA      LONG =
Array[800, 800, 10]
```

Exercise


Try reading some of the data that you have downloaded (or have been supplied with) into SSWIDL. Query the data with the **help** command.

4 Plotting SDO data

4.1 Basic plotting

Once data has been read in to SSWIDL, the first thing that many people want to do is look at the image. This image may not come out too well (e.g., figure 1 top-left), perhaps it is too dim or bright. This is because the data has been scaled linearly between the lowest and highest value pixels. Alternative minimum and maximum values can be supplied to select a contrast range. This is done with the min and max keywords, e.g.,

```
IDL> plot_image, data, min=100, max=2500
```

This scales the image so that any pixel value below 100 is black and any above 2500 is white. Values in-between are linearly scaled to different shades of grey (e.g., figure 1 top-right). It may be useful to find the minimum and maximum pixel values of an image by using the `minmax` command:

```
IDL> print,minmax(data)
0      15800
```

Sometimes it may be appropriate to apply a nonlinear scaling. The easiest way to do this is to use the appropriate

IDL function on the data. Some common functions are

```
IDL> plot_image, sqrt(data), min=sqrt(100), max=sqrt(2500) IDL> plot_image, alog(data),
min=alog(100), max=alog(2500)
```

which give a square root and logarithmic scaling accordingly (e.g., figure 1 bottom-left and right). Note that the function must also be applied to the min/max scalings as well. Be careful to avoid illegal scalings (e.g., the square root of a negative number or the log of zero) as this may produce unexpected results.

4.2 Plotting one image from a larger array

Often, multiple images may have been read in to a single array, e.g.,

```
IDL> help, adata
```

ADATA LONG = Array[4096, 4096, 10] To plot one of these images, the array must be appropriately indexed, e.g., IDL> plot_image, adata(*,*,2), min=100, max=2500 plots the third index in the sequence (IDL counts from 0). The *s indicate that all columns and rows of the image will be plotted. Changing the 2 to a different number will plot a different image in the sequence.

Exercise

Try plotting some of the data that you have read in with different scalings.

4.3 Plotting part of an image

Plotting the complete image is fine, but often only a certain part of the image is interesting, and it would be useful to fill the graphics window with only that part of the image. This can be done by replacing the *s in the above command to the desired cutout range, e.g.,

```
IDL> plot_image, data(1950:2549,1100:1699), min=100, max=2500
IDL> plot_image, adata(1950:2549,1100:1699,2), min=100, max=2500
```

This command plots the part of the image between pixel number 1950 and 2549 (inclusive) in the x-direction, and between 1100 and 1699 (inclusive) in the y-direction, as shown in figure 2. The numbers can be changed to represent the desired region within the SDO image.




Figure 2: AIA 193 Å data plotted showing (left) the full disk; (right) a cutout of an active region from the disk. The displayed cutout is shown as the white box in the left image.

Exercise

Try plotting different parts of images that you have previously read in.

4.4 Plotting images in colour

The standard IDL `loadct` command can be used to change the colour table used for the image. The default is greyscale, but can be changed by

The standard IDL `loadct` command can be used to change the colour table used for the image. The default is greyscale, but can be changed by

IDL> `loadct`

0-	B-W LINEAR	14-	STEPS	28-	Hardcandy
1-	BLUE/WHITE	15-	STERN SPECIAL	29-	Nature
2-	GRN-RED-BLU-WHT	16-	Haze	30-	Ocean
3-	RED TEMPERATURE	17-	Blue - Pastel - R	31-	Peppermint
4-	BLUE/GREEN/RED/YE	18-	Pastels	32-	Plasma
5-	STD GAMMA-II	19-	Hue Sat Lightness	33-	Blue-Red
6-	PRISM	20-	Hue Sat Lightness	34-	Rainbow
7-	RED-PURPLE	21-	Hue Sat Value 1	35-	Blue Waves
8-	LINEA	22-	Hue Sat Value 2	36-	Volcano
	GREEN/WHITE				
9-	EXPONENTI	23-	Purple-Red + Stri	37-	Waves
	GRN/WHT				
10-	GREEN-PINK	24-	Beach	38-	Rainbow18
11-	BLUE-RED	25-	Mac Style	39-	Rainbow + white
12-	16 LEVEL	26-	Eos A	40-	Rainbow + black
13-	RAINBOW	27-	Eos B		

Enter table number:

and entering the desired colour table number when prompted. If the desired colour table number is known, this can be directly entered with, e.g.,

and entering the desired colour table number when prompted. If the desired colour table number is known, this can be directly entered with, e.g.,

```
IDL> loadct, 3
```

to load in the red temperature colour table.




Figure 3: AIA 193 Å
Data plotted with (left) a greyscale colour table; (right) the proposed AIA 193 Å color table.

However, this is restricted to the default IDL colour tables and may not include the desired scheme. SDO/AIA images have a set of proposed colour schemes for different spectral pass-bands. These can be accessed using the command `aia_lct`, e.g.,

```
IDL> aia_lct, rr, gg, bb, wavelnth=193, /load
```

loads the proposed colour table for the 193 pass-band into IDL (it also stores the red, green, and blue component mixes in the arrays `rr`, `gg`, `bb`).

So a 193 image can be plotted by doing the following

```
IDL> read_sdo, 'aia_193_file.fits', index, data  
IDL> aia_lct, rr, gg, bb, wavelnth=193, /load  
IDL> plot_image, sqrt(data), min=sqrt(100), max=sqrt(2500)
```

and typical results can be seen in figure 3.

Exercise

Try plotting images and sub-field images that you have previously tried using different colour tables. Do different colour tables need different scalings?

4.5 Plotting HMI data

Data from SDO/HMI can be read in to SSWIDL and plotted in exactly the same way as described for the AIA data above, i.e.,

```
IDL> read_sdo, 'hmi_file.fits', mindex, mdata
```

However, there are a couple of things to bear in mind when using HMI data. First, the data may be upside down. This can be checked by examining the fits header

```
IDL> print,mindex.crota2  
180
```




Figure 4: HMI data may be stored upside down in the fits file (left), this can easily be corrected for (right) using

the rotate command. Comparison with the corresponding AIA 193 Å

observation in figure 3 indicates that

active regions in the rotated image are co-located with their coronal emission.

This is the rotation angle of the image and if it is 180 then it is upside down. This can easily be corrected with

```
IDL> mdata = rotate(temporary(mdata), 2)
IDL> plot_image, mdata, min=-10000, max=10000
```

as shown in figure 4, though this must be done on an image by image basis for a sequence of images, e.g.,

```
IDL> nims=n_elements(mindex)
IDL> for i=0,nims-1 do mdata(*,*,i)=rotate(temporary(mdata(*,*,i)),2)
```

Exercise

Try reading in and plotting some HMI data, rotating as appropriate. Plot a corresponding AIA image in a different graphics window and see if the locations of the active regions agree.

5 Examining the fits headers

So far the fits headers have been loaded in to SSWIDL and the index.crota2 keyword has been mentioned. However, the information within the fits header can be far more useful than this. Contained within the fits header is a wealth of information about the corresponding observation such as the instrument, time taken, pass band, resolution, and so on.

5.1 Browsing the fits headers

To examine fits header information use the help command with the /struct keyword, i.e.,

```
IDL> help, index, /str
** Structure MS_020517472001, 176 tags, length=1560, data length=1500: SIMPLE INT 1
BITPIX      LONG 32
NAXIS       LONG 2
NAXIS1      LONG 4096
NAXIS2      LONG 4096
EXTEND      INT 1
DATE_OBS    STRING '2010-06-13T23:59:30.63Z'
.
.
.
```

This lists all the available keywords, their data type, and their values. For example, naxis gives the number of dimensions of the observation, naxis1 and naxis2 give the array size of the stored data. Note, /str is short for /structure.

Individual elements of an array of fits headers can be accessed by specifying the desired number, e.g.,

```
IDL> help, index(4), /str
```

5.2 Useful AIA and HMI fits keywords

There are only a small number of standard fits keywords that all fits files must have, most of the keywords are chosen by the specific instrument team depending on the capabilities of the instrument itself (for example spectroscopic data may require different information than imager data), many instrument teams will produce a fits keywords specification document. However, there are some fairly common keywords that many instrument teams use.

There are too many AIA and HMI keywords to describe in full here, but some of the more useful ones are described in table 1. A complete list can be found on the JSOC website.

The help command allows a quick look at all of the fits keywords, but it is also useful to be able to access individual keywords. This can be done as follows:

```
IDL> print, index.date_obs
2010-06-13T23:59:30.63Z
IDL> print, aindex(4).date_obs
2010-06-13T00:00:54.60Z IDL> xcen = index.crpix1
IDL> ycen = index.crpix2
IDL> print, xcen, ycen
2047 2053
IDL> i193 = where(aindex.wavelnth eq 193) IDL> print, i193
```

Keyword

naxis1 **Type**

long **Purpose**

pixel size of image in x-direction

naxis2 long pixel size of image in y-direction

telescope string telescope/observatory name (e.g., SDO)

instrument string instrument name (e.g., AIA)

wavelnth long wave band of images (e.g., 193)

waveunit string units of wavelnth (e.g., angstrom)

date_obs string date and time of start of observation

t_obs string date and time of middle of observation

exptime float exposure time of observation - AIA only

cadence long cadence of image sequence - HMI only

crpix1 long reference pixel in the x-direction (1 is centre of lefthand pixel)

crpix2 long reference pixel in the y-direction (1 is centre of bottom pixel)

crval1 long location of reference pixel in x-direction (e.g., 0 is Sun centre)

crval2 long location of reference pixel in y-direction (e.g., 0 is Sun centre)

cdelt1 float pixel size in x-direction

cdelt2 float pixel size in y-direction

ctype1 string coordinate system for crval1

cunit1	string	units of crval1 and cdelt1
cunit2	string	units of crval2 and cdelt2
crota2	double	rotation angle about reference pixel
r_sun	float	radius of the Sun in image pixels
rsun_ref	double	radius of the Sun in metres - AIA only
rsun_obs	float	radius of the Sun in observing units (e.g., arcseconds)
contentstring	data product (e.g., magnetogram) - HMI only	
bunit	string	units of image data (e.g., Gauss) - HMI only

Table 1: Description of some useful fits keywords for SDO/AIA and SDO/HMI data.

Examine some of the fits headers in data that you have read into SSIDL and pick out the values of useful keywords.

5.3 Using fits keywords to refine data searches

This last line of the previous case

```
IDL> i193 = where(aindex.wavelnth eq 193)
```

indicates how the fits headers can be used for a more refined search. Consider the following example

```
IDL> afiles = findfile('aia*.fits')
IDL> read_sdo, afiles, aindex, adata, /nodata
IDL> print, aindex.wavelnth
171  211  94  335  1600  193  304  131
171  211  94  335  1700  193  304  131
171  211  94  335  1600  193  304  131
171  211  94  335  1700  193  304  131
171  211  94  335  1600  193  304  131
171  211  94  335  1700  193  304  131
171  211  94  335  1600  193  304  131
IDL> i304 = where(aindex.wavelnth eq 304)
```

```
IDL> afiles304 = afiles(i304)
IDL> read_sdo, afiles304, aindex304, adata304
IDL> aia_lct, rr, gg, bb, wavelnth=304, /load
IDL> plot_image, sqrt(adata304(*,*,0)), min=sqrt(10), max=sqrt(1000)
```

This identifies a set of AIA files and reads in the fits headers only. Printing the wave band information shows that the fits files contain images taken in a range of different pass bands. The where function can be used to

find the indices of all of the 304 Å

images which is used to extract the subset of the afiles array relating to

304 Å data. This subset is then read in and the first image plotted (in colour).

Exercise

Use the where function to perform more refined searches on your fits files.

5.4 Making plot axes more meaningful




Figure 5: An AIA 304 Å

image displayed using plot image (left) without the use of any extra arguments,

(right) using the fits header to convert the scale to arcseconds.

The fits keywords can be used to convert the axes of the plot into more meaningful units, e.g.,

```
IDL> plot_image, sqrt(adata304(*,*,0)), min=sqrt(10), max=sqrt(1000), $  
origin=-[(aindex(0).crpix1-1)*aindex(0).cdelt1, $  
(aindex(0).crpix2-1)*aindex(0).cdelt2], $  
scale=[aindex(0).cdelt1,aindex(0).cdelt2], $  
xtitle='X-position (arcseconds)', $  
ytitle='Y-position (arcseconds)'
```

which produces the image in figure 5 right.

Extra arguments have been added to the plot image command. The scale argument takes a two element array containing the x- and y-scales of the images, this is stored in the cdelt1 and cdelt2 keywords. The origin argument is also a two element array that defines the lower-left hand corner of the axes. This can be calculated using the negative location of Sun centre given by -crpix1 and -crpix2 and multiplying by the pixel size to convert to arcseconds. Note, the aindex(0).crpix1-1 and aindex(0).crpix2-1 adjusts for the fact that crpix counts the first pixel as 1 where SSIDL counts it as 0. A quick check of

crval1, crval2, cunit1 and cunit2

```
IDL> print, aindex(0).crval1, aindex(0).crval2
0      0
IDL> print, aindex(0).cunit1, ' ', aindex(0).cunit2 arcsec arcsec
```

confirms that the reference pixel is indeed Sun centre and the units are arcseconds. The xtitle and ytitle argument allow labelling of the x- and y-axes.

Exercise

Try modifying the axes of plots of data that you have previously read in.

5.5 Working with date/time keywords

The data/time fits keywords (e.g., date obs) are given as strings, e.g.,

```
IDL> print,index.date_obs
2010-08-09T19:49:00.34Z
```

This is fine for human inspection or labelling of plots, but sometimes it is useful to be able to perform time-based calculations, and a string is not so useful for doing this.

A date/time string can be converted into seconds (from a standard reference time) using the anytim2tai function, i.e.,

```
IDL> secs = anytim2tai(aindex304.date_obs) IDL> print, secs
1.6600746e+09      1.6600746e+09      1.6600747e+09      1.6600748e+09
1.6600748e+09      1.6600749e+09      1.6600749e+09
```

Now these values may not initially seem useful as the reference time was sufficiently far back that the values have become quite large. However, this can be brought under control by choosing a more useful reference time and subtracting this from the above result. For example

```
IDL> tref='2010-08-09T19:00:00.00Z' IDL> sref=anytim2tai(tref)
IDL> secs = anytim2tai(aindex304.date_obs) - sref
IDL> print, secs
2948.1300      3008.1200      3068.1300      3128.1200
3188.1300      3248.1200      3308.1300
IDL> mins = secs/60.0
IDL> print,mins
49.135500      50.135333      51.135500      52.135333
53.135500      54.135333      55.135500
```

gives the observation times in seconds and minutes respectively from the new reference time.

This information might be useful for refining a search (e.g., identifying an image every 10 minutes), or for plotting quantities that vary with time.

Exercise

Manipulate the date/time information from fits headers that you have read in to SSWIDL.

5.6 Rotating HMI data

Section 4.5 explained how sometimes HMI data might be rotated by 180° and how to rotate the image to agree with the AIA observations, i.e.,

```
IDL> mdata = rotate(temporary(mdata), 2)
IDL> plot_image, mdata, min=-10000, max=10000
```

This rotation will most likely change the location of the reference pixel. If the fits headers are to be used for further analysis, then it may be sensible to update this information when the image is rotated, i.e.,

```
IDL> mindex.crpix1 = mindex.naxis1 - mindex.crpix1 + 1
IDL> mindex.crpix2 = mindex.naxis2 - mindex.crpix2 + 1
IDL> mindex.crota2 = mindex.crota2 - 180
```

Again, the +1 is due to the crpix keywords counting the centre of the first pixel as 1.

Exercise

Read in an HMI file, rotate the data and modify the keywords, then plot the image with the origin at Sun-centre and the axes in arcseconds.

6 Tracking a region across the disk

Section 3 showed how a sub-field of an SDO observation could be read into SSWIDL. Picking a fixed region for analysis over a few minutes is fine, but over longer periods of time the feature of interest will likely move out of the sub-field as the Sun rotates. In order to follow a feature, its position as it rotates across the solar disk must be calculated. This can be done using the rot xy function. Given a position in arcseconds on the solar disk, a reference time, and a required time, this function will calculate the location of the reference position at the required time (which can be before the reference time as well as after). For example

```
IDL> xcen=-50.0
IDL> ycen=100.0
IDL> tref='2010-08-09T12:00:00.00Z' IDL> treq='2010-08-10T12:00:00.00Z'
IDL> npos = rot_xy(xcen,ycen,tstart=tref,tend=treq) IDL> print,npos
163.612
100.515
```

In this case the reference position is (-50, 100) arcseconds from disk centre at a reference time of 12:00 on 9th August. The position of this region at 12:00 on 10th August is given by the result of rot xy, and is (163.612, 100.515) arcseconds from disk centre.

6.1 Co-aligning a pair of observations

When a feature is being tracked in actual SDO observations, the information in the fits headers can be used to calculate the required clipping region for each file.

First a reference image and region must be selected, e.g.,

```
IDL> afiles=findfile('/archive/aia_set_*.fits') IDL> help, afiles
AFILES          STRING      = Array[18]
```

```
IDL> read_sdo, afiles(8), rindex, rdata
IDL> plot_image, sqrt(rdata), min=sqrt(100), max=sqrt(2500)
IDL> plot_image, sqrt(rdata(2130:2429,2350:2649)), min=10, max=50
```

From plotting sub-fields, a cutout of 2130-2429 pixels in the x-direction, and 2350-2649 pixels in the y-direction has been selected, which is a 300×300 pixel cutout. The centre of this cutout in the x- and y-directions is then given by

```
IDL> xcenp = (2130.0 + 2429.0)/2.0
IDL> ycenp = (2350.0 + 2649.0)/2.0
IDL> print, xcenp, ycenp
2279.50      2499.50
```

and the size of the cutout is

```
IDL> xsize = 2429.0 - 2130.0 + 1.0
IDL> ysize = 2649.0 - 2350.0 + 1.0
IDL> print, xsize, ysize
300.000      300.000
```

The position of the centre of the cutout can now be converted into arcseconds by

```
IDL> xcena = (xcenp - rindex.crpix1 + 1)*rindex.cdelt1
IDL> ycena = (ycenp - rindex.crpix2 + 1)*rindex.cdelt2
IDL> print, xcena, ycena
140.11821    268.53490
```

which has the associated reference time given by

```
IDL> tref = rindex.date_obs
IDL> print, tref
2010-08-09T00:00:07.84Z
```




Figure 6: An AIA 193 Å clip at (left) 00:00 on 9th August 2010, and (right) the tracked sub-field 1 day later.

The corresponding sub-field for a different observation can be calculated as follows

```
IDL> read_sdo, afiles(10), cindex, cdata, /nodata
IDL> treq = cindex.date_obs

IDL> print, treq
2010-08-10T00:00:07.84Z
IDL> npos = rot_xy(xcena, ycena, tstart=tref, tend=treq) IDL> print, npos
330.983
273.516
```

which is the new position of the centre of the sub-field in arcseconds. This can be converted into pixel position by

```
IDL> xcenp2 = npos(0)/cindex.cdelt1 + cindex.crpix1 - 1
IDL> ycenp2 = npos(1)/cindex.cdelt2 + cindex.crpix2 - 1
IDL> print, xcenp2, ycenp2
2597.5673    2507.8009
```

which with xsize and ysize can be used to calculate the location of the lower-lefthand corner as follows

```
IDL> xlo = round(xcenp2 - xsize/2.0) IDL> ylo = round(ycenp2 - ysize/2.0) IDL> print, xlo, ylo
2448    2358
```

The required sub-field can now be read in using read_sdo

```
IDL> read_sdo, afiles(10), cindex, cclip, xlo, ylo, xsize, ysize
IDL> plot_image, sqrt(cclip), min=sqrt(100), max=sqrt(2500)
```

assuming that the two observations are at the same resolution. Typical results can be seen in figure 6.

Exercise

Select a reference image, choose a region of interest, and track the region into a second image at a different time.

6.2 Co-aligning a sequence of observations

The above methodology is okay for co-aligning a pair of images, but repeating it for a sequence of observations is not necessarily the most efficient approach. Instead, sensible use of loops and arrays with a little programming may be better.

With the reference clip selected above, consider the following temporary program for tracking the region in all of the observations in afiles.

```
IDL> .r
- nf = n_elements(afiles)
- ccube = fltarr(xsize, ysize, nf)
- for n=0, nf-1 do begin
- read_sdo, afiles(n), cindex, cdata, /nodata
- npos = rot_xy(xcena, ycena, tstart=tref, tend=cindex.date_obs)
- xcenp2 = npos(0)/cindex.cdelt1 + cindex.crpix1 - 1
- ycenp2 = npos(1)/cindex.cdelt2 + cindex.crpix2 - 1
- xlo = round(xcenp2 - xsize/2.0)
- ylo = round(ycenp2 - ysize/2.0)
- read_sdo, afiles(n), cindex, cclip, xlo, ylo, xsize, ysize
- ccube(*,*,n) = cclip
- endfor

- end
```

This tracks and clips the region of interest from each of the files in turn, and stores the results in the three- dimensional array ccube.

If the fits headers are required, then these should also be collected within the loop, as keywords such as crpix1, crpix2, naxis1, and naxis2 are modified by read sdo to reflect the clip taken.

Note, while this tracking has been presented as a temporary program, for more general use it may be worth converting it into a user defined program that can be easily reused in different cases.




Figure 7: An AIA 193 Å clip tracked at 12 hour intervals starting at 00:00 on 5th August 2010. If there are not too many images, then they can all be viewed by something like

```
IDL> !p.multi=[0,6,3]
IDL> for n=0, nf-1 do plot_image, sqrt(ccube(*,*,n)), $
min=sqrt(100), max=sqrt(2500)
```

where !p.multi specifies the number of plots to a page (start with the first location, with 6 columns and 3 rows, e.g., figure 7). Otherwise, some other form of presentation (such as a movie) is required.

Note, IDL will persist with the multiplot window - wrapping round to the first location once it reaches the end

- until cancelled. This can be done with

```
IDL> !p.multi = 0
```

Exercise

Using the sequence of AIA 193 Å

files on the memory stick, select a reference image and region of interest,

and clip all of the other files to that region. Plot the region as you see fit.

Can you extract the same region from the corresponding HMI files on the memory stick.

Hint, as HMI and AIA are at different resolutions, the required HMI x- and y-sizes will need to be recalculated, this can be done with

```
- xsize2 = xsize*rindex.cdelt1/cindex.cdelt1
- ysize2 = ysize*rindex.cdelt2/cindex.cdelt2
```

Also, remember that HMI data may be upside down, so the appropriate HMI fits keywords in `cindex` will have to be modified before using them for calculation. Once the new centre pixel has been calculated (`xcenp2`, `ycenp2`), this must be rotated once more for selecting the correct portion of the upside down data in the file, i.e.,

```
- xcenp2rot = cindex.naxis1 - xcenp2 - 1.0
- ycenp2rot = cindex.naxis2 - ycenp2 - 1.0
```

which can be used to calculate `xlo` and `ylo`

Finally, once the clip has been extracted from a file, it should be rotated before being stored in the `ccube` array.

7 Making SDO image output

Displaying SDO data within SSWIDL is fine for personal viewing of SDO data, but sooner or later a standalone image file will be required for logbooks, publications, talks, posters, and so on.

There are two basic options, a vector format such as postscript, or a bit-mapped format such as PNG or JPEG. In both cases the actual SDO data is bit-mapped, any text, plot axes, plot annotations will come out smoother in printed material in vector form, whereas correctly sized bit-mapped output tend to be better on computer screens (e.g., talks, web pages).

7.1 Output as postscript




Figure 8: SDO data can be easily output into postscript files suitable for inclusion in text documents.

To write to a postscript file (e.g., figure 8), something like the following would be required:

```
IDL> set_plot, 'ps'
IDL> device, file='304output.ps', xsize=4, ysize=4, /inches, $
/color, bits=8
```



```

IDL> aia_lct, rr, gg, bb, wavelnth=304, /load
IDL> plot_image, sqrt(adata304(*,*,6)), min=sqrt(10), max=sqrt(1000), $
origin=-[(aindex304(6).crpix1-1)*aindex304(6).cdelt1, $
(aindex304(6).crpix2-1)*aindex304(6).cdelt2], $

scale=[aindex304(6).cdelt1,aindex304(6).cdelt2], $
xtitle='X-position (arcseconds)', $
ytitle='Y-position (arcseconds)' IDL> device, /close
IDL> set_plot, 'x'

```

This creates a file that, when printed, will produce a 4 × 4 inch colour plot of the file in question, with the x- and y-axes in arcseconds.

Any of the plot image commands found in this primer can be substituted into this set of commands, additionally, oplot and other graphics commands may appear as well.

The postscript file generated above will be quite large (perhaps around 33 MB), so it is worth considering whether the image needs to be at full resolution. If a lower-resolution is acceptable, then the image can be resized with either of

```

IDL> lrdata1 = rebin(adata(*,*,6), 1024, 1024) IDL> lrdata2 = congrid(adata(*,*,6), 1233, 1233)

```

The rebin command is when the desired resize is a simple fraction/multiple of the original size (e.g., $\frac{1}{4} \times$, $\frac{1}{3} \times$, $\frac{1}{2} \times$, $2 \times$, $3 \times$, $4 \times$, $8 \times$, etc), or a whole pixel multiple/fraction. The congrid function will resize to arbitrary sizes.

Exercise

Try writing out postscript images of different observations at different resolutions. These can be viewed under Linux with something like gv.

7.2 Output as PNG, JPEG, etc




Figure 9: SDO data can be easily output into JPEG and PNG files suitable for inclusion on web pages and in talks.

The following is one method of writing to a JPEG file (e.g., figure 9)

```
IDL> window, 30, xsize=4096, ysize=4096, /pixmap
IDL> aia_lct, rr, gg, bb, wave=304, /load
IDL> tv, bytscl(sqrt(addata(*,*,6)), min=sqrt(10), max=sqrt(1000)) IDL> trimg = tvrd(/true)
IDL> wdel, 30
IDL> write_jpeg, 'test_im_304.jpg', trimg, true=1
```

The first line creates an imaginary graphics window in memory (reading/writing to an actual graphics window can sometimes be flawed), the third line writes the image to the imaginary window (without any axes or text), the fourth reads from the window into an array, the fifth deletes the imaginary window (it is a good idea to tidy up memory usage when it is no longer needed), and the sixth line writes to a JPEG file (note, some versions of IDL will write the file upside down, so the keyword /order must be included to correct this).

The quality of a JPEG can be controlled with the quality argument, e.g.,

```
IDL> write_jpeg, 'test_im_304.jpg', trimg, true=1, quality=85
```

The quality argument takes a value between 0 (poor) and 100 (very high), and defaults to 75 if not specified. The higher the quality, the larger the file size.

Writing a PNG has almost the same syntax, i.e.,

```
IDL> write_png, 'test_im_304.png', trimg
```

Writing to and from a graphics window (even an imaginary one) is a useful way to build up a plot, but can sometimes be slow. A quicker way to write just the image is

```
IDL> img = bytscl(sqrt(addata(*,*,6)), min=sqrt(10), max=sqrt(1000)) IDL> trimg =
bytarr(3,4096,4096)
IDL> trimg(0,*,*) = rr(img) IDL> trimg(1,*,*) = gg(img) IDL> trimg(2,*,*) = bb(img)
IDL> write_png, 'test_im_304.png', trimg
```

This method does not use any graphics windows (imaginary or otherwise) at all.

As with postscript files, it is worth considering the resolution of the image being written. Computer screens have resolutions considerably smaller than 4096×4096 , and it can often be sensible to scale the image to the desired size at the outset. This can be done using rebin or congrid as shown above.

Major Exercise

Write a program to generate a long-term plot intensity plot using SDO AIA 193 Data. The plot should calculate the total intensity of a small region of an AIA image vs the total magnetic flux.

Use the data intensity over lifetime

1. open and name program file
 2. list input and output variables at top of header
 3. assign needed variables
 4. create body of program that will calculate values for all images in array
 - read in data or download data
 - assign a value to a subset of that data cube over the entire lifetime
 - end loop
- plot values
- label graphs
 - create legend

Try writing out JPEG and PNG images of different observations at different resolutions.

Appendix

8 Response function of the AIA telescopes

8.1 Wavelength response function

The AIA telescopes select the different wavelength bands using broad band filters. Each filter has a specific response function which is typically centred on the wavelength of the observed spectral line. The wavelength response functions are plotted in Figure 10 for six characteristic wavelengths.

To obtain the wavelength response functions try the following:

```
IDL> wave_resp = aia_get_response() IDL> help, wave_resp, /str
IDL> help, wave_resp.a171, /str
```

which can be plotted with something like

```
IDL> plot, wave_resp.a171.wave, wave_resp.a171.ea
IDL> plot, wave_resp.a171.wave, wave_resp.a171.ea, xrange=[150,200]
```

It is noticeable that the filter is broader for larger wavelengths. It is clear that the 171 Å filter has a secondary peak at 175 Å. Currently there is no response functions for the visible spectral lines.




Figure 10: Wavelength response functions for six characteristic pass-bands, these are 94 Å , 131 Å , 171 Å , 193 Å , 211 Å , and 304 Å .

8.2 Temperature Response function

A spectral line has a specific temperature of formation. Nevertheless, the broad band filters are responsible for a temperature response function resulting from the wavelength range observed. The different temperature response functions are summarised in Figure 11 for six characteristic wavelengths.

The temperature response functions can be obtained with

```
IDL> temp_resp = aia_get_response(/temp) IDL> help, temp_resp, /str
IDL> help, temp_resp.a171, /str
IDL> plot, temp_resp.a171.logte, temp_resp.a171.tresp
```

Most of the temperature profiles show that an AIA image does not correspond to a unique temperature, but mostly to two temperatures and a broad range of temperature. It is important for the interpretation of the AIA images to understand at which temperature the plasma is observed. For instance a plasma seen in the 94 Å filter has a temperature of 1 million degrees or close to 10 million degrees.

Exercise

Plot and examine the wavelength and temperature responses for other pass-bands. Can you modify the temper-




Figure 11: Temperature response functions for six characteristic pass-bands, these are 94 Å°, 131 Å°, 171 Å°, 193 Å°, 211 Å°, and 304 Å°.

ature plots so that the $\log_{10}(T_e)$ axis becomes a plain temperature axis?